



HOPPER INFORMATION SERIES

08 / FIDUCIAL MARKERS

AprilTags with Hopper

Visual IDs for detection, centering and 2D heading alignment.

tag36h11



tag36h11 ID 0

ID + orientation



AprilTags were built to give robots reliable visual landmarks



The original goal: print an artificial feature that a camera can identify and localize—even when natural visual features are unreliable.

A printed tag can become a shared coordinate reference

LOCALIZATION

- Estimate a robot or camera pose relative to a known landmark.

NAVIGATION + DOCKING

- Center on a landing pad, charging station, doorway, or work cell.

CALIBRATION

- Relate cameras, robot frames, and measurement rigs with known geometry.

MANIPULATION

- Identify bins, tools, parts, or target objects for a robot arm.

SLAM + GROUND TRUTH

- Supply repeatable landmarks while testing perception and state estimation.

AR + HUMAN INTERFACES

- Anchor digital information to a physical place or object.

A tag is useful because its identity and geometry are designed—not discovered by chance.



A visual ID designed for robots



HOPPER FAMILY

- tag36h11
- IDs 0 through 586
- Black and white only
- Up to 3 payload-bit errors accepted

WHY FIDUCIALS

- Known geometry.
- Unique machine-readable ID.
- Orientation from one image.
- No battery or radio on the tag.


Family chooses the codebook; ID chooses one tag inside it

FAMILY	CODE DESIGN	WHEN IT FITS
tag16h5	Small code, fewer IDs	Legacy / compact demonstrations
tag25h9	More bits and separation	Legacy balance of size and robustness
tag36h11	36 data bits · minimum Hamming distance 11	Hopper Studio: IDs 0–586
tagStandard41h12	Modern standard layout	Upstream default for most new work
tagCircle49h12	Circular, space-efficient layout	Small circular objects

Never mix families in one detector configuration: the same ID number in another family is a different code.




How Hopper Studio detects a tag





Coordinates and pose in Hopper Studio



APRILTAG RESULT


- id + family + hamming
- four corners + center in pixels
- bounding box
- centerX / centerY: -100..100
- yaw: normalized around +/-180 deg

DO NOT OVERCLAIM

- Yaw is 2D image-plane orientation.
- It is not full 3D pose or aircraft heading.
- No distance or altitude is returned.
- centerOnAprilTag never lands.



Print cleanly and place deliberately



tag36h11 ID 7


PRINT IN HOPPER STUDIO

- Vision Testing -> AprilTag Detection.
- Choose an ID from 0-586.
- Generate PDF for a full-page US Letter vector tag.
- Print at 100% scale with a clean white margin.

PLACE FOR THE CAMERA

- Keep the sheet flat and well lit.
- Avoid glare, folds, shadows and clipped margins.
- Start large and close; test before increasing height.
- Keep paper and people clear of propellers.

From a printed ID to a mission decision



Block patterns

- scan for AprilTags
- camera sees AprilTag with ID any / 0–586
- center on AprilTag with power, center slack, angle slack, and lost-tag limit

Hopper Studio provides a relative visual landmark—not global position, altitude, or collision avoidance.



Reliable tags need reliable experiments

BEFORE FLIGHT

- Confirm the family is tag36h11.
- Test the intended ID, size, angle and lighting.
- Keep the full border and quiet zone in frame.
- Use a lost-tag limit and an overall timeout.
- Plan a safe fallback land.

SOURCES AND FURTHER READING

University of Michigan APRIL Lab - AprilTag

<https://april.eecs.umich.edu/software/apriltag>

AprilTag 2 paper

<https://april.eecs.umich.edu/media/pdfs/wang2016iros.pdf>

Hopper Studio detector and printable tag generator

[lib/apriltags.ts](#), [lib/vision.ts](#) and [README.md](#)

DETECT -> CENTER -> ALIGN -> DECIDE

The mission still owns height, obstacle clearance and landing.